

Networking

Networking

- [Cisco ASA Cli](#)
- [Cisco ASA Site to Site](#)
- [IPv4 Subnet Mask Cheat Sheet](#)
- [Linux Routing](#)
- [Juniper Cli](#)
- [SAN - Dell Equallogic CLI Notes](#)
- [Dell PowerConnect Switch CLI](#)
- [Linux - Netplan](#)
- [Cisco ASA - AnyConnect VPN](#)
- [Improve Pfsense PPPOE +1Gbps](#)

Cisco ASA Cli

Static NAT (SNAT)

```
object network obj-192.168.1.100
host 192.168.1.100
nat (inside,outside) static 192.166.1.101 dns
```

PAT

Allow outside connections targeting TCP port 80 to redirect to internal port 8080.

```
object network obj-192.166.1.101-srv_8080
host 192.166.1.101
nat (inside,outside) static 192.166.1.101 service tcp 8080 http
```

DNAT

In the example bellow, the subnet will be on a port channel named inside2 and will have a obj-group called net-local2

```
interface port-channel 150
nameif inside2
security-level 100
ip address 172.10.10.0 255.255.255.0
```

```
object-group network net-local2
network-object 172.10.10.0 255.255.255.0
```

after-auto Inserts the rule at the end of section.

You can translate all addresses on the source interface by specifying source dynamic any mapped_obj

```
nat (inside2,outside) after-auto source dynamic net-local2 interface dns
```

PAT connections will be visible in ***show xlate***

```
fw1# show xlate
TCP PAT from inside2:172.10.10.11/51995 to outside:199.199.199.100/51995
flags riD
idle 0:05:37 timeout 0:00:30
```

For more advanced configs, refer to article below:

<https://www.cisco.com/c/en/us/td/docs/security/asa/asa-command-reference/I-R/cmdref2/n.html>

Configuring Static PAT as a Twice NAT/Manual NAT

```
object network local-192.168.1.100
host 192.168.1.100

object network external-2.2.2.2
host 2.2.2.2

object service https
service tcp source eq https

object service tcp_8443
service tcp source eq 8443

nat (inside,outside) source static local-192.168.1.100 external-2.2.2.2 service tcp_8443 https
```

DHCP Server

```
dhcpd address 10.20.106.240-10.20.106.253 inside
dhcpd dns 8.8.8.8 8.8.4.4
dhcpd enable inside
```

ASDM

```
asdm image disk0:/asdm-X.bin
```

```
http server enable 8080  
http <whitelist-ip> 255.255.255.0 OUTSIDE
```

```
username admin password PASSWORD privilege 15
```

```
https://<asa ip>:8080
```

Allow non-connected subnets

```
arp permit-nonconnected
```

The ASA ARP cache only contains entries from directly-connected subnets by default. You can enable the ARP cache to also include non-directly-connected subnets. We do not recommend enabling this feature unless you know the security risks. This feature could facilitate denial of service (DoS) attack against the ASA; a user on any interface could send out many ARP replies and overload the ASA ARP table with false entries.

You may want to use this feature if you use:

- Secondary subnets.
- Proxy ARP on adjacent routes for traffic forwarding.

Route LAN to remote subnet on physical port

```
interface GigabitEthernet1/8  
  description remote  
  no nameif  
  no security-level  
  no ip address  
  
interface GigabitEthernet1/8.100  
  description Public VLAN 100 remote  
  vlan 100
```

```
nameif remote
no security-level
ip address 192.168.1.2 255.255.255.0

object network local-net
  subnet 192.168.2.0 255.255.255.0

object network remote-net
  subnet 192.168.3.0 255.255.255.0

access-list inbound extended permit ip object local-net object remote-net
nat (inside,remote) source static local-net local-net destination static remote-net remote-net

route remote 192.168.3.0 255.255.255.0 192.168.1.1 1
```

In this example you will be able to connect to "192.168.3.0/24" from your local "192.168.2.0/24" subnet using the 192.168.1.2 port, the remote port will be on the same vlan using the IP 192.168.1.1

Object Groups ASA

```
object-group service http-https tcp
port-object eq www
port-object eq https
```

```
object-group network webservers
network-object host 192.168.1.101
network-object host 192.168.1.102
network-object host 192.168.1.103
```

```
access-list OUTSIDE-IN extended permit tcp any object-group webservers object-group http-https
access-group OUTSIDE-IN in interface outside
```

packet-tracer

```
packet-tracer input inside icmp 192.168.1.100 8 0 8.8.8.8
packet-tracer input outside tcp 8.8.8.8 80 192.168.1.100 80
```

Backup/Restore

Create a Backup

```
copy running-config disk0:/backup-2017-00-00
```

Restore a backup

```
copy disk0:/backup-2017-08-18 startup-config
reload
```

Allow FTP passive ports

The firewall will block this data communication because it will start from a different source port (20 instead of 21). The purpose therefore of the inspect ftp command on the Cisco ASA is to listen for the initial Command FTP traffic (on port 21) and dynamically open a secondary Data connection between FTP server and client (from port 20). This will allow FTP communication to work. If you disable FTP inspection with the no inspect ftp command, outbound users can start connections only in passive mode, and all inbound FTP is disabled.

```
policy-map global_policy
  class inspection_default
    no inspect ftp
```

Mitigating attack traffic

DEFINE TRAFFIC

First of all we define which traffic the MPF policy will be applied to. In the example below we exclude the host 8.8.8.8 whilst inspecting all other traffic.

```
access-list mpf-policy-acl extended permit ip any any
```

CREATE CLASS-MAP

Next we assign the previously created access-list to a class-map.

```
class-map mpf-policy
match access-list mpf-policy-acl
```

CREATE POLICY-MAP

Then a policy-map is created and the necessary connection limits defined.

```
policy-map mpf-policy-map
class mpf-policy
set connection conn-max 9500
set connection embryonic-conn-max 5000
set connection per-client-embryonic-max 100
set connection per-client-max 300
```

Allow LAN management over VPN

```
management-access inside
nat (inside,any) source static obj-LANSUBNET obj-LANSUBNET destination static obj-VPNSUBNET
obj-VPNSUBNET route-lookup
http <VPNSUBNET> 255.255.255.0 inside
ssh <VPNSUBNET> 255.255.255.0 inside
```

Failover

To run on the Standby FW

```
failover active
```

Licensing Info

Different ASA models have different licensing options. To see what the limits of the active license, use the following:

```
sh version
```

Links

<https://www.cisco.com/c/en/us/support/security/asa-5500-series-next-generation-firewalls/products-command-reference-list.html>

<https://wiki.myhypervisor.ca/books/networking/page/cisco-asa-site-to-site>

<https://www.cisco.com/c/en/us/support/security/asa-5500-series-next-generation-firewalls/products-installation-and-configuration-guides-list.html>

<https://www.cisco.com/c/en/us/support/security/asa-5500-series-next-generation-firewalls/products-configuration-examples-list.html>

Cisco ASA Site to Site

Verification: NAT or transparent mode

Value should return (Firewall mode: Router)

```
show firewall
```

Always do a backup!!!

```
copy running-config disk0:/running-config-backup-DDMMYYYY
```

ACL / No NAT Rules

Change net-local and and remote for local and remote IP

You do not need to create a object for the LAN if you already have one for another tunnel //
You also **can not** have 2 tunnels with the same remote IP's

```
object-group network net-local  
network-object 10.1.2.0 255.255.255.0  
object-group network net-remote  
network-object 192.168.1.0 255.255.255.0
```

Create a cryptomap ACL

```
access-list outside_1_cryptomap extended permit ip object-group net-local object-group net-remote
```

Allow traffic between the two sites to bypass NAT

Always check the name of interface on the port channel, the tunnel will not work if your interface is named inside3

```
nat (inside,outside) source static net-local net-local destination static net-remote net-remote
```

IKEV1 - Route based

```
tunnel-group 199.168.1.100 type ipsec-l2l
tunnel-group 199.168.1.100 ipsec-attributes
    ikev1 pre-shared-key *****

crypto ikev1 policy 10
    authentication pre-share
    encryption aes-256
    hash sha
    lifetime 3600
    group 5

crypto ipsec ikev1 transform-set ESP-AES-256-MD5 esp-aes-256 esp-md5-hmac

crypto ipsec profile vpn1
    set ikev1 transform-set ESP-AES-256-SHA
    set security-association lifetime seconds 3600

interface Tunnel1
    nameif int-vpn1
    ip address 192.168.0.1 255.255.255.252
    tunnel source interface outside
    tunnel destination 199.168.1.100
    tunnel mode ipsec ipv4
    tunnel protection ipsec profile vpn1

access-list vpn1-inbound extended permit ip any any
access-list vpn1-outbound extended permit ip any any
access-group vpn1-inbound in interface int-vpn1
access-group vpn1-outbound out interface int-vpn1

route int-vpn1 10.10.10.0 255.255.255.0 192.168.0.2 1
```

IKEV1 - Policy based

Create the tunnel group, and configure the pre-shared key. (In ex; 199.168.1.100 = Remote WAN)

```
tunnel-group 199.168.1.100 type ipsec-l2l
tunnel-group 199.168.1.100 ipsec-attributes
pre-shared-key INSERT_SECURE_PRE_SHARED_KEY_HERE
```

Declare the most common transform sets (only do once).

```
crypto ipsec ikev1 transform-set ESP-AES-128-SHA esp-aes esp-sha-hmac
crypto ipsec ikev1 transform-set ESP-AES-128-MD5 esp-aes esp-md5-hmac
crypto ipsec ikev1 transform-set ESP-AES-192-SHA esp-aes-192 esp-sha-hmac
crypto ipsec ikev1 transform-set ESP-AES-192-MD5 esp-aes-192 esp-md5-hmac
crypto ipsec ikev1 transform-set ESP-AES-256-SHA esp-aes-256 esp-sha-hmac
crypto ipsec ikev1 transform-set ESP-AES-256-MD5 esp-aes-256 esp-md5-hmac
crypto ipsec ikev1 transform-set ESP-3DES-MD5 esp-3des esp-md5-hmac
crypto ipsec ikev1 transform-set ESP-DES-SHA esp-des esp-sha-hmac
crypto ipsec ikev1 transform-set ESP-DES-MD5 esp-des esp-md5-hmac
crypto ipsec ikev1 transform-set ESP-3DES-SHA esp-3des esp-sha-hmac
```

Phase 1 parameters

```
crypto ikev1 policy 10
authentication pre-share
encryption 3des
hash sha
group 2
lifetime 86400
### Enable ikev1 on the outside interface - THIS JUST NEED TO BE CONFIGURED ONCE YOU SETUP THE
FIRST VPN
crypto ikev1 enable outside
crypto ikev1 am-disable #(! Main mode remove this line for aggressive mode)
```

Enable ikev1 on the outside interface -**THIS JUST NEED TO BE DONE ON THE FIRST IKEV1 VPN**

```
crypto ikev1 enable outside
```

Set main mode // Do not include this line for aggressive mode

This is a global setting, if you add the line bellow in a ASA that contains a tunnel that uses aggressive mode, it will break the other tunnel

```
crypto ikev1 am-disable
```

Phase 2 parameters

If you remove the ACL used by a tunnel, it will **remove** the line `crypto map outside_map 1 match address ACL_NAME` // Only set **PFS** if configured on the remote side, else skip the line

```
crypto map outside_map 1 match address outside_1_cryptomap
crypto map outside_map 1 set peer 199.168.1.100
crypto map outside_map 1 set transform-set ESP-3DES-SHA
crypto map outside_map 1 set pfs group2
crypto map outside_map 1 set security-association lifetime seconds 3600
```

Enable the crypto map in the outside interface - **THIS JUST NEED TO BE DONE ON THE FIRST IKEV1 VPN**

```
crypto map outside_map interface outside
```

IKEV2

Create the tunnel group, and configure the pre-shared key. (In ex; 199.168.1.100 = Remote WAN)

```
group-policy GroupPolicy_IKEv2 internal
group-policy GroupPolicy_IKEv2 attributes
vpn-idle-timeout none
vpn-tunnel-protocol ikev2

tunnel-group 199.168.1.100 type ipsec-l2l
tunnel-group 199.168.1.100 general-attributes
default-group-policy GroupPolicy_IKEv2
tunnel-group 199.168.1.100 ipsec-attributes
ikev2 remote-authentication pre-shared-key ***
ikev2 local-authentication pre-shared-key ***
```

Declare the transform sets

```
crypto ipsec ikev2 ipsec-proposal ESP-AES-256-SHA
  protocol esp encryption aes-256
  protocol esp integrity sha-1
```

Phase 1 parameters

```
crypto ikev2 policy 20
  encryption aes-256
  integrity sha
  group 2
  prf sha
  lifetime seconds 86400
```

Phase 2 parameters

```
crypto map outside_map 1 match address outside_1_cryptomap
crypto map outside_map 1 set pfs
crypto map outside_map 1 set peer 199.168.1.100
crypto map outside_map 1 set ikev2 ipsec-proposal ESP-AES-256-SHA
crypto map outside_map 1 set security-association lifetime seconds 3600
crypto ikev2 enable outside
```

NAT

If the request needs to go over the nated IP, do not use the ACL / Nat rules above, configure something like this:

```
nat (INSIDE,OUTSIDE) source static PRENAT_IP POSTNAT_IP destination static DESTINATION_IP
DESTINATION_IP
```

```
access-list outside_1_cryptomap extended permit ip host NATTED_SOURCE_IP host
NATTED_DESTINATION_IP
```

Troubleshooting/Debug

Useful links:

- http://www.cisco.com/en/US/products/ps6120/products_tech_note09186a00807e0aca.shtml#solunf
- http://www.cisco.com/c/en/us/td/docs/security/asa/asa72/configuration/guide/conf_gd/ike.html
- http://www.cisco.com/c/en/us/td/docs/security/asa/asa90/configuration/guide/asa_90_cli_config/vpn_ike.html#pgfId-1042302

Test connection (Run command 2x)

```
packet-tracer input inside icmp 10.1.2.100 8 0 192.168.1.100
```

Check IKEV1 Logs

```
debug crypto ikev1 127
```

Check IKEV2 Logs

```
debug crypto ikev2 protocol
```

Clear tunnel session

```
clear isakmp sa
```

Find pre-shared key

```
more system:running-config | grep pre-shared
```

Check basic VPN session information

```
sh isakmp sa
```

Check details on VPN session (Detailed)

```
show vpn-sessiondb detail ra-ikev1-ipsec
```

Capture traffic for the ACL related to the VPN

```
capture test access-list outside_1_cryptomap interface inside real-time
```

Once you are done, always remember to save your config

IPv4 Subnet Mask Cheat Sheet

CIDR	Subnet Mask	Total IPs	Usable IPs
/32	255.255.255.255	1	1
/31	255.255.255.254	2	2*
/30	255.255.255.252	4	2
/29	255.255.255.248	8	6
/28	255.255.255.240	16	14
/27	255.255.255.224	32	30
/26	255.255.255.192	64	62
/25	255.255.255.128	128	126
/24	255.255.255.0	256	254
/23	255.255.254.0	512	510
/22	255.255.252.0	1024	1022
/21	255.255.248.0	2048	2046
/20	255.255.240.0	4096	4094
/19	255.255.224.0	8192	8190
/18	255.255.192.0	16,384	16,382
/17	255.255.128.0	32,768	32,766
/16	255.255.0.0	65,536	65,534
/15	255.254.0.0	131,072	131,070
/14	255.252.0.0	262,144	262,142
/13	255.248.0.0	524,288	524,286
/12	255.240.0.0	1,048,576	1,048,574
/11	255.224.0.0	2,097,152	2,097,150
/10	255.192.0.0	4,194,304	4,194,302
/9	255.128.0.0	8,388,608	8,388,606
/8	255.0.0.0	16,777,216	16,777,214
/7	254.0.0.0	33,554,432	33,554,430
/6	252.0.0.0	67,108,864	67,108,862
/5	248.0.0.0	134,217,728	134,217,726

CIDR	Subnet Mask	Total IPs	Usable IPs
/4	240.0.0.0	268,435,456	268,435,454
/3	224.0.0.0	536,870,912	536,870,910
/2	192.0.0.0	1,073,741,824	1,073,741,822
/1	128.0.0.0	2,147,483,648	2,147,483,646

Linux Routing

Routing

View routes

ip route

```
ip route
```

Adding a route

```
ip addr add 192.168.1.100/24 dev eth0
```

Add a gateway

```
ip route add default via 192.168.1.1 dev eth0
```

Add a route of a subnet to a gateway

```
ip route add 10.1.2.0/24 via 10.1.2.1 dev eth0
```

null route (blackhole)

```
ip route add blackhole 10.1.2.130 # For an IP
ip route add blackhole 10.1.2.10/24 # For a subnet
ip route del blackhole 10.1.2.130 # Remove from blackhole
```

null route an ip list

```
for string in $(cat ips.txt); do ip route add blackhole $string; done
```

Juniper Cli

Display

Show Display configuration

```
show configuration | display set
```

Show display detail configuration

```
show configuration | display detail
```

show arp macs

```
show ethernet-switching table
```

File

To navigate the file system you can do

```
file list /?
```

Backup

Backup configuration in homedir

```
save router-config-name
```

Backup active configuration in homedir

```
run show configuration | save backup-name
```

Create a rescue configuration

If the active configuration is corrupted, the device will automatically load the filenameed rescue.gz in the `/config` directory as the active configuration:

```
file copy /config/juniper.conf.gz /config/rescue.gz
```

Completely replace the current candidate configuration with a previously stored file.

```
load override /var/tmp/router-config  
commit
```

Check configuration before a commit:

```
commit check
```

Rollback

Show rollabcks

```
rollback ?
```

Compare active config with rollback X

```
show | compare rollback X
```

Compare candidate config with active configuration

```
show | compare
```

rollback 0 references the active configuration, so the following command is equivalent to the previous one

```
rollback X
```

Replace candidate configuration with rollback X:

We start by loading rollback X

```
rollback X
```

Checking everything is fine

```
show  
show | compare
```

If everything is fine:

```
commit
```

Commit version during X minutes

You need to confirm with a commit, or modification will be rollback after X minutes.

```
commit confirmed X
```

Show pending auto commits (and commits history):

```
show system commit
```

Auto commit at a particular time:

```
commit at 02:00:00  
show system commit
```

Adding a Vlan

```
set vlans VLAN444 vlan-id 444
```

You will then need to add the vlan to an uplink, in this example the uplink is aggregated

```
set interfaces ae48 unit 0 family ethernet-switching vlan members 444
```

Vlan Switching

For Ex33 switches, auto-negotiation is not required.

Setting port to access on a vlan

```
delete interfaces xe-0/0/0  
set interfaces xe-0/0/0 ether-options auto-negotiation  
set interfaces xe-0/0/0 unit 0 family ethernet-switching interface-mode access  
set interfaces xe-0/0/0 unit 0 family ethernet-switching vlan members 4082  
set interfaces xe-0/0/0 unit 0 family ethernet-switching recovery-timeout 300
```

Setting port to aggregated

```
delete interfaces xe-0/0/0
set interfaces xe-0/0/0 description member-ae0
set interfaces xe-0/0/0 ether-options auto-negotiation
set interfaces xe-0/0/0 ether-options 802.3ad ae0
```

Configuring the LACP on the aggregated link

```
set interfaces ae0 description "aggregate-link"
set interfaces ae0 aggregated-ether-options link-speed 10g
set interfaces ae0 aggregated-ether-options lacp active
set interfaces ae0 unit 0 family ethernet-switching interface-mode trunk
set interfaces ae0 unit 0 family ethernet-switching vlan members 4040
set interfaces ae0 unit 0 family ethernet-switching vlan members 4041
set interfaces ae0 unit 0 family ethernet-switching storm-control default
set interfaces ae0 unit 0 family ethernet-switching recovery-timeout 300
```

```
delete protocols rstp interface xe-0/0/0
delete protocols rstp interface xe-1/0/0
set protocols rstp interface ae0 edge
set protocols rstp interface ae0 no-root-port
```

Firewall Rules

```
set interfaces vlan unit [VAN_ID] family inet filter input INBOUND-TRAFFIC
set firewall family inet filter INBOUND-TRAFFIC term name-of-rule from source-address [IP]/32
set firewall family inet filter INBOUND-TRAFFIC term name-of-rule from destination-address
[IP]/32
set firewall family inet filter INBOUND-TRAFFIC term name-of-rule from destination-port 22
set firewall family inet filter INBOUND-TRAFFIC term name-of-rule then accept
```

SAN - Dell Equallogic CLI Notes

```
group1> member select MEMBERNAME eth sel 1 NEWIPADDRESS NETMASK  
group1> grpparams group-ipaddress IPADDRESS
```

Then go back and fix the other network.

```
group1> member select MEMBERNAME eth sel 0 NEWIPADDRESS NETMASK
```

Then set the new default gateway

```
group1> member select MEMBERNAME def-gateway IPADDRESS
```

Supported Update Paths

<https://eqsupport.dell.com/support/download.aspx?id=6442456361>

Reset

```
Press Ctrl/p  
setenv RESETPASSWORD 1  
reload  
account select grpadmin passwd  
group1> reset
```

Change VLAN

```
grpparams dcb def-vlan-id 609
```

Downgrade FW

THIS WILL WIPE THE SAN

Transfer FW, login as "root / grpadmin"

```
update.sh -override-downgrade
```

Dell PowerConnect Switch CLI

Adding a VLAN to a port-channel

Add the VLAN to the DB

```
vlan database  
vlan 4082
```

Check ARP response from uplinks

```
show bridge address-table  
show bridge address-table vlan <vlan-num>
```

Add the VLAN to the port-channel for the UPLINKS

```
interface port-channel 10  
switchport trunk allowed vlan add 4082
```

Add the vlan to the port-channel for the port that needs the vlan

```
interface port-channel 15  
switchport trunk allowed vlan add 4082
```

Save

```
copy running-config startup-config
```

Linux - Netplan

This new tool replaces the static interfaces (**/etc/network/interfaces**) on ubuntu 18.04

DHCP

```
network:
  version: 2
  renderer: networkd
  ethernets:
    ens33:
      dhcp4: yes
      dhcp6: no
```

Static IP

```
network:
  version: 2
  renderer: networkd
  ethernets:
    ens33:
      dhcp4: no
      dhcp6: no
      addresses: [192.168.1.2/24]
      gateway4: 192.168.1.1
      nameservers:
        addresses: [8.8.8.8,8.8.4.4]
    ens34:
      dhcp4: no
      dhcp6: no
      addresses: [192.168.1.3/24]
```

Apply changes

```
netplan apply
```

netplan apply does not require a service restart or a reboot

NetworkManager

Configuring with wifi nic

```
network:  
  version: 2  
  renderer: NetworkManager  
  wifis:  
    wlx7c8bca0d69b6:  
      dhcp4: no  
      addresses: [192.168.1.100/24]  
      gateway4: 192.168.1.1  
      nameservers:  
        addresses: [192.168.1.1,8.8.8.8]  
      access-points:  
        Raj:  
          password: MyPass
```

Links:

<https://netplan.io/>

Cisco ASA - AnyConnect VPN

Enable webvpn

```
webvpn
  enable outside
  anyconnect image disk0:/anyconnect-win-4.0.00061-k9.pkg 1
  anyconnect image disk0:/anyconnect-macosx-i386-4.0.00061-k9.pkg 2
  anyconnect image disk0:/anyconnect-linux-64-4.0.00061-k9.pkg 3
  anyconnect enable
  tunnel-group-list enable
  cache
    disable
  error-recovery disable
```

```
ip local pool webvpn-ippool 172.28.38.10-172.28.38.250 mask 255.255.255.0
```

```
object network anyconnect_subnet
  subnet 172.28.38.0 255.255.255.0
```

```
object network internal_subnet
  subnet 172.28.37.0 255.255.255.0
```

```
nat (any,outside) source static internal_subnet internal_subnet destination static
anyconnect_subnet anyconnect_subnet
```

```
group-policy SSLAccess internal
group-policy SSLAccess attributes
  address-pools value webvpn-ippool
  vpn-tunnel-protocol ssl-client
  split-tunnel-policy tunnelspecified

tunnel-group SSLAccess type remote-access
tunnel-group SSLAccess general-attributes
  default-group-policy SSLAccess
  tunnel-group SSLAccess webvpn-attributes
group-alias VPN
```

```
username username password hhcZmv0YAh1e1 mschap privilege 0
username username attributes
vpn-group-policy SSLAccess
```

SplitACL (optional)

```
group-policy SSLAccess attributes
dns-server value 8.8.8.8 8.8.4.4
split-tunnel-network-list value Split-ACL
```

```
access-list Split-ACL standard permit 172.28.38.0 255.255.255.0
```

Improve PFsense PPPOE +1Gbps

To improve speeds from 500Mbps on PFsense, Change the following values:

```
vi /boot/loader.conf.local
```

```
net.isr.dispatch=deferred  
net.isr.maxthreads="-1"  
net.isr.bindthreads="1"
```

In System > Advanced > Miscellaneous

Enable PowerD and AC Power to Maximum

Proxy Support

Proxy URL
Hostname or IP address of proxy server this system will use for its outbound Internet access.

Proxy Port
Port where proxy server is listening.

Proxy Username
Username for authentication to proxy server. Optional, leave blank to not use authentication.

Proxy Password
Password for authentication to proxy server. Confirm

Load Balancing

Load Balancing Use sticky connections
Successive connections will be redirected via gateways in a round-robin manner with connections from the same source being sent via the same gateway. This "sticky connection" will exist as long as there are states that refer to this connection. Once the states expire, so will the sticky connection. Further connections from that host will be redirected via the next gateway in the round robin. Set the source tracking timeout for sticky connections in seconds. By default this is 0, so source tracking is removed as soon as the state expires. Setting this timeout higher will cause the source/destination relationship to persist for longer periods of time.

Power Savings

PowerD Enable PowerD 
The powerd utility monitors the system state and sets various power control options accordingly. It offers four modes (maximum, minimum, adaptive and hiadaptive) that can be individually selected while on AC power or batteries. The modes maximum, minimum, adaptive and hiadaptive may be abbreviated max, min, adp, hadp. Maximum mode chooses the highest performance values. Minimum mode selects the lowest performance values to get the most power savings. Adaptive mode attempts to strike a balance by degrading performance when the system appears idle and increasing it when the system is busy. It offers a good balance between a small performance loss for greatly increased power savings. Hiadaptive mode is alike adaptive mode, but tuned for systems where performance and interactivity are more important than power consumption. It raises frequency faster, drops slower and keeps twice lower CPU load.

AC Power 

Battery Power

Unknown Power